

Installation guide for Meta Quest 3 / 3S with MHMS in Shared Mode

1) Download & unzip the Magic Horizons VR software

- ▶ Use the Quest 3 / 3S download link in our **download portal** on our website with the credentials we have sent you to download our VR software on your deployment computer
- ▶ It will be a large file **in a zipped format** like **95 to 100 GB**
- ▶ Please make sure that you have a **good internet connection**
- ▶ There must be **twice as much free space** on your internal or external hard disc on your computer when you unzip the file (approx. **190 - 200 GB**)
- ▶ **Unzip** the downloaded file on your computer. Afterwards you can delete the zip file
- ▶ In case your Windows PC has problems with unzipping files with **long names** use the program “7 Zip”:
<https://7-zip.org/>
- ▶ Inside the unzipped “Deploy” folder you will see then 2 files:
 - ▶ The Magic Horizons media storage folder with all content
 - ▶ The file with the extension APK at the end which is the app itself

📁 MagicHorizons(MediaStorage)

📄 Deploy_B2BPlayer_Magic_Horizons_MetaQuest3_100_exp_200T_TABLET_SW_TE_V10.apk

2) Only in case an older Magic Horizons software is already installed – delete it first

- ▶ Only in case there is already an **older Magic Horizons software** installed on the Quest headset, the Quest **must be reset first**
- ▶ Please go to your Meta MHMS account:
 - ▶ Go to “Manage devices”
 - ▶ Select the headset you want to reset
 - ▶ There are 3 dots at the right side of the selected headset
 - ▶ Click: **“Release device”** (trash symbol)

3) Installation of the Magic Horizons APK

- ▶ Here is our APK **online link**: https://download.datamagichorizons.com/Deploy_B2BPlayer_Magic_Horizons_MetaQuest3S_126_300_TE_V26e.apk
- ▶ Please install the APK first via our online link by creating a new **“app preset”** like you install other APKs via MHMS
- ▶ Please refer to the Meta MHMS instructions
- ▶ Do **not** use the APK included in our download folder

4) Start the Magic Horizons app

- ▶ Start the Magic Horizons app like you start all other apps via MHMS.


5) License key activation

Magic Horizons License key activation in the Quest 3 / 3S:

- ▶ After the Magic Horizons app has started the first time: type in the correct **license key** which you have received from Magic Horizons
- ▶ The license key consists of **4 digits, a hyphen** and again of **4 digits**, for example: **y23g-14rt**
- ▶ Please make sure to type in **exactly in this format** the correct numbers or letters including the hyphen of the license key
- ▶ Make sure that a **0** (= zero) and an **o** (= letter "O") as well as an **i** (= letter "i") or an **l** (= letter "l") are not mixed up
- ▶ It is mandatory to start the Magic Horizons app **first**

6) Press "Allow" to allow access to the Magic Horizons content

- ▶ When the permission prompt appears press: **Allow** or the little **on** switch in the allow-field to to give access to the internal media
- ▶ The prompt appears only for the first start
- ▶ **Allow** is important - otherwise the Magic Horizons media is not played back!




Press: allow

7) Install the Magic Horizons Media Storage folder

Installation of the MagicHorizons(MediaStorage) folder:

- ▶ Connect your Quest 3 / 3S to your deployment computer
- ▶ Inside Quest 3 / 3S press on **allow** to allow the USB connection to a PC or Mac
- ▶ Place the **MagicHorizons(MediaStorage)** folder exactly in: **Android / media**
- ▶ The MagicHorizons(MediaStorage) folder must be placed exactly in this location and must not be renamed
- ▶ Otherwise the Magic Horizons app would not work correctly
- ▶ Do not **move, remove** or **delete** the “ MagicHorizons(MediaStorage)“ folder, the “Lic“ folder and the “UserPlaylist“ folder inside Android / media - otherwise the Magic Horizons software will not work properly



Please place the
MagicHorizons(MediaStorage)
folder in:
Android / media

8) Final test

- ▶ After a successful installation switch **off** the Quest 3 / 3S headset by long pressing the On/Off button
- ▶ Then switch **on** the VR headset again
- ▶ Launch the Magic Horizons App
- ▶ Finally do a **quick check** in “Single Application“ : start one **nature video**, one **interactive application** and one **binaural beat** to see that the Magic Horizons app and the corresponding content is loaded correctly
- ▶ An **infinitely turning blue wheel** will indicate that the MagicHorizons(MediaStorage) folder has not been completely installed or has not been installed in the correct location: Android / media
- ▶ In this case please redo the installation as described on page 3

9) Important information about the Shared Mode in MHMS

- When clicking shortly on the right controller on the Meta button, a slide pops up offering “Resume“ to go back to Magic Horizons or offering at the right bottom a white exit icon
- If you see this slide you must always press “**Resume**“.
- **Never click on the Exit icon** to end the Meta Shared Mode
- If you would click on the exit symbol, a second slide would pop up:
- “Do you want to end the session? This device will be restarted and any user data stored on it will be cleared“.
- Never click on “**End Session**“:
- **To end the Magic Horizons app** on a Meta Quest 3 / 3S headset in Shared Mode:
- **Always switch off** the headset by long pressing the On / Off switch at the left side
- Thank you very much!



Magic Horizons GmbH
Lohweg 35
85375 Neufahrn
Germany

Email: support@magic-horizons.com
Web: <https://magic-horizons.com/en/>