

## Build 2026


### Installation guide for **Pico G3 / G3 Plus** (= Easy Plus)



THE STEPS IN THESE INSTRUCTIONS MUST BE FOLLOWED EXPLICITLY

#### 1) Preparation: Developer Mode and newest PUI

- ▶ How to activate the developer mode inside the Pico G3:
- ▶ Click on the **gear wheel** symbol for “Settings” **in the dock** or if your VR glasses are in **Kiosk Mode** **double click** the **home button** on the controller to open the Pico “Quick settings” menu. In the “Quick settings” menu click on the **gear wheel** symbol at the top right.
- ▶ In the Pico settings go to: “General” on the left side / scroll almost all the way down on the right side to select: **About** / inside “About” scroll down to **Software Version** and then click **10 times** on the software version number to start the developer mode.
- ▶ Then the new entry **Developer** appears on the left side at the bottom.
- ▶ To check if you are on the newest **PUI** (= the Pico operating system) go to **Settings / General / System Version**. If needed downloaded the newest PUI. Therefore your VR glasses have to be connected with WIFI and the internet.




## 2) Download & unzip the Magic Horizons VR software

- ▶ Use the download link which Magic Horizons has provided you via email to download our VR software.
- ▶ It will be a large file in **zipped format** like **90 to 100 GB**. Please make sure that you have a **good internet** connection.
- ▶ There must be **twice as much free space** on your internal or external hard disc on your PC or Mac when you unzip the file (approx. **190 GB+**).
- ▶ **Unzip** the downloaded file on your PC or Mac. You can delete the Zip file afterwards.
- ▶ Inside the unzipped “Deploy” folder you will see then **2 files**:
  - ▶ The Magic Horizons media storage folder (which has approx. **90 - 100 GB**).
  - ▶ The APK (= the app) itself, which has approx. only **700 MB**.




## 3) Download Sidequest + connect Pico VR glasses

- ▶ For installing the APK (= the app itself) you need the free program **Sidequest**.
- ▶ We recommend to use the **Advanced Installer** of Sidequest.
- ▶ For Windows PC or Mac download **Sidequest** here: <https://sidequestvr.com/setup-howto>
- ▶ Connect the **Pico G3** via USB-C to your PC or Mac.
- ▶ For a **Mac** you need a free program like Android File Transfer.
- ▶ Start the **Sidequest** program on your PC or Mac.
- ▶ Wait until **Sidequest** has detected the Pico G3.
- ▶ You see a **green** indicator at the top left showing that the VR glasses are successfully connected.




#### 4) First: install the Magic Horizons APK via SideQuest


- It is **mandatory** that the Magic Horizons App (= the APK file) is installed **first** on the VR glasses.
- Click on the **Install** button of **Sidequest**.
- Select the “Deploy\_B2BPlayer\_Magic\_Horizons ... .apk“ file on your PC or Mac.
- In case an older Magic Horizons APK is already installed on the VR glasses please uninstall this old version first (described on page 5).




- ▶ Wait for approx. 2-3 minutes while the APK installation is in progress.
- ▶ **Do not interrupt** the installation process and do not start any other tasks on your computer while the installation is running.



- ▶ When the message jumps to **green** the installation is finished.



- ▶ Switch to “App Overview Tab“ to check that the Magic Horizons App is installed.




## 5) Kiosk Mode and Encrypted version with license key

- ▶ Start the Magic Horizons app manually from your **app library browser** if not in Kiosk Mode.
- ▶ To put the Magic Horizons App into **Kiosk mode**:
  - ▶ Click on the dock on the **settings menu symbol** (= gear wheel).
  - ▶ Go to **Developer / Business Settings / Home Screen**.
  - ▶ Here select the **Magic Horizons App** as Home screen (= **Kiosk**) app if you want to run it in Kiosk mode.
  - ▶ The VR glasses will restart automatically.
- ▶ If you have an **Encrypted** Magic Horizons VR software: type in the **license key** you received from Magic Horizons. This is mandatory **after the first start** of the Magic Horizons software.
- ▶ The license key consists of **4 digits, a hyphen & again of 4 digits**, for example: **y23g-14rt**.
- ▶ The license key consists only of **small letters** and **numbers**.
- ▶ The license key must be typed in the VR glasses **exactly in this** format.
- ▶ Do not forget the **hyphen** between the two blocks of the four digits.
- ▶ Make sure that an **0** (= zero) and an **O** (= letter “O“) as well as an **i** (= letter “i“) and an **I** (= letter “I“) are not mixed up.
- ▶ After the first start of the Magic Horizons app a **permission prompt** appears.
- ▶ Press **Allow** to access the internal media.
- ▶ Pressing **Allow is important** – otherwise the media is not played back!

## 6) Second: install the Media Storage folder

After the Magic Horizons APK is installed the second step is the installation of the **Magic Horizons (MediaStorage)** folder:

- Place the MagicHorizons(MediaStorage) folder in: **Android / data / com.magichorizons.b2bpico / files**.
- The MagicHorizons(MediaStorage) folder must be placed **exactly** in this location and must not be renamed – otherwise the Magic Horizons app would not work correctly.



- After a successful installation of the Media Storage folder switch **off** the VR glasses by long pressing the On/Off button.
- Switch **on** the VR glasses again by long pressing the On/Off button.
- If the Magic Horizons App is not in Kiosk (Home) mode start the Magic Horizons app in the app library launcher.
- Finally do a **quick check** in "Single Applications" : start one **nature video**, one **interactive application** and one **binaural beat** to see that the app and the corresponding content is loaded correctly.

